



- German Emission Inventory Goals & Demands
- Database System
 Dataflow & Structure, Databases of spatial distribution
- Software MESAP
 Databases CSE & Point Source (Mr. Schellmann)



German Emission Inventory

Goals

- Central data management (making of an inventory)
- Performance of the reporting obligations

Demands


- Transparency
- Flexibility
- Efficiency
- Consistency
- Completeness



Database System

Dataflow & Structure

Databases of spatial distribution






Database System

Dataflow & Structure

Databases of spatial distribution




Modul SuDa



Compilation of Distribution Parameters

- Statistical data (e.g. number of inhabitants)
- Calculated data of emissions
- Use of areas for agriculture
- Information on coal mining, air traffic





Gridding of Emissions

- Determination of any grid cell in EMEP-coordinates
- Calculation of emissions of district areas according to the distribution information of SuDa
- Distribution of emissions to grid cells




Distribution of Emissions on Grid Cells:

Area sources

$$Emi_{grid} = Emi_{district} * \frac{area_{grid}}{area_{district}}$$

Line sources

$$Emi_{grid} = Emi_{DE} * \frac{DTV_{grid}}{DTV_{DE}}$$






Gridding of Emissions on EMEP50-Grid Cells


Composition of EMEP50 grid cells out of the 1 km * 1 km grid

Basic principle: boundaries of districts gridded on 1 km * 1 km grid cells



Distribution of the Daily Traffic Volume (DTV) on the EMEP50 grid cells

Basic principle: DTV on 1 km * 1 km grid cells





Example of Datapool SuDa (Surrogate Data)

Regionalisation of emissions of passenger car traffic on motorways

1990: Activities of emission register

1995: Daily Traffic Volume (DTV)

1991 - 1994: linear interpolation of the ratio of the national totals

1996 - 1999: Regionalisation with the data material of 1995



Calculation of emissions of district areas:

$$Emi_{district} = Emi_{DE} * \frac{DP_{district}}{DP_{DE}}$$

For each SNAP the appropriate distribution parameter (DP) is used.

Accumulation of the emissions after specification.

